

TABLE xx - Row xx: CHAM

	xx0	xx1	xx2	xx3	xx4	xx5	xx6	xx7
0	 000	 016	 032	 048	 064	080	096	112
1	 001	 017	 033	 049	 065	081	097	113
2	 002	 018	 034	 050	 066	082	098	114
3	 003	 019	 035	 051	 067	083	099	115
4	 004	 020	 036	 052	 068	084	100	116
5	 005	 021	 037	 053	 069	085	101	117
6	 006	 022	 038	 054	 070	086	102	118
7	 007	 023	 039	 055	 071	087	103	119
8	 008	 024	 040	 056	 072	088	104	120
9	 009	 025	 041	 057	 073	089	105	121
A	 010	 026	 042	 058	074	090	106	122
B	 011	 027	 043	 059	075	091	107	123
C	 012	 028	 044	 060	 076	092	108	124
D	 013	 029	 045	061	 077	093	109	125
E	 014	 030	 046	062	 078	094	110	126
F	 015	 031	 047	 063	 079	095	111	127

G = 00
P = 00

TABLE xx - Row xx: CHAM

dec	hex	Name	dec	hex	Name
000	00	CHAM LETTER A	091	5B	(This postion shall not be used)
001	01	CHAM LETTER I	092	5C	(This postion shall not be used)
002	02	CHAM LETTER U	093	5D	(This postion shall not be used)
003	03	CHAM LETTER E	094	5E	(This postion shall not be used)
004	04	CHAM LETTER AI	095	5F	(This postion shall not be used)
005	05	CHAM LETTER O	096	60	(This postion shall not be used)
006	06	CHAM LETTER KA	097	61	(This postion shall not be used)
007	07	CHAM LETTER KHA	098	62	(This postion shall not be used)
008	08	CHAM LETTER GA	099	63	(This postion shall not be used)
009	09	CHAM LETTER GHA	100	64	(This postion shall not be used)
010	0A	CHAM LETTER NGUE	101	65	(This postion shall not be used)
011	0B	CHAM SIGN NG	102	66	(This postion shall not be used)
012	0C	CHAM LETTER NGA	103	67	(This postion shall not be used)
013	0D	CHAM LETTER CHA	104	68	(This postion shall not be used)
014	0E	CHAM LETTER CHHA	105	69	(This postion shall not be used)
015	0F	CHAM LETTER JA	106	6A	(This postion shall not be used)
016	10	CHAM LETTER JHA	107	6B	(This postion shall not be used)
017	11	CHAM LETTER NHUE	108	6C	(This postion shall not be used)
018	12	CHAM LETTER NHA	109	6D	(This postion shall not be used)
019	13	CHAM LETTER NHJA	110	6E	(This postion shall not be used)
020	14	CHAM LETTER TA	111	6F	(This postion shall not be used)
021	15	CHAM LETTER THA	112	70	(This postion shall not be used)
022	16	CHAM LETTER DA	113	71	(This postion shall not be used)
023	17	CHAM LETTER DHA	114	72	(This postion shall not be used)
024	18	CHAM LETTER NUE	115	73	(This postion shall not be used)
025	19	CHAM LETTER NA	116	74	(This postion shall not be used)
026	1A	CHAM LETTER DDA	117	75	(This postion shall not be used)
027	1B	CHAM LETTER PA	118	76	(This postion shall not be used)
028	1C	CHAM LETTER PPA	119	77	(This postion shall not be used)
029	1D	CHAM LETTER PHA	120	78	(This postion shall not be used)
030	1E	CHAM LETTER BA	121	79	(This postion shall not be used)
031	1F	CHAM LETTER BHA	122	7A	(This postion shall not be used)
032	20	CHAM LETTER MUE	123	7B	(This postion shall not be used)
033	21	CHAM LETTER MA	124	7C	(This postion shall not be used)
034	22	CHAM LETTER BBA	125	7D	(This postion shall not be used)
035	23	CHAM LETTER YA	126	7E	(This postion shall not be used)
036	24	CHAM LETTER RA	127	7F	(This postion shall not be used)
037	25	CHAM LETTER LA			
038	26	CHAM LETTER VA			
039	27	CHAM LETTER SSA			
040	28	CHAM LETTER SA			
041	29	CHAM LETTER YA			
042	2A	CHAM SIGN ANUSVARA			
043	2B	CHAM SIGN VISARGA			
044	2C	CHAM VOWEL SIGN A			
045	2D	CHAM VOWEL SIGN I			
046	2E	CHAM VOWEL SIGN II			
047	2F	CHAM VOWEL SIGN EI			
048	30	CHAM VOWEL SIGN U			
049	31	CHAM VOWEL SIGN UU			
050	32	CHAM VOWEL SIGN OEU			
051	33	CHAM VOWEL SIGN OE			
052	34	CHAM VOWEL SIGN OOE			
053	35	CHAM VOWEL SIGN E			
054	36	CHAM VOWEL SIGN EE			
055	37	CHAM VOWEL SIGN O			
056	38	CHAM VOWEL SIGN OO			
057	39	CHAM VOWEL SIGN AI			
058	3A	CHAM VOWEL SIGN AU			
059	3B	CHAM VOWEL SIGN UE			
060	3C	CHAM VOWEL SIGN UUE			
061	3D	(This postion shall not be used)			
062	3E	(This postion shall not be used)			
063	3F	CHAM VIRAMA			
064	40	CHAM DIGIT ZERO			
065	41	CHAM DIGIT ONE			
066	42	CHAM DIGIT TWO			
067	43	CHAM DIGIT THREE			
068	44	CHAM DIGIT FOUR			
069	45	CHAM DIGIT FIVE			
070	46	CHAM DIGIT SIX			
071	47	CHAM DIGIT SEVEN			
072	48	CHAM DIGIT EIGHT			
073	49	CHAM DIGIT NINE			
074	4A	(This postion shall not be used)			
075	4B	(This postion shall not be used)			
076	4C	CHAM STOP SIGN			
077	4D	CHAM PARAGRAPH SIGN			
078	4E	CHAM BEGIN TEXT MARK			
079	4F	CHAM END TEXT MARK			
080	50	(This postion shall not be used)			
081	51	(This postion shall not be used)			
082	52	(This postion shall not be used)			
083	53	(This postion shall not be used)			
084	54	(This postion shall not be used)			
085	55	(This postion shall not be used)			
086	56	(This postion shall not be used)			
087	57	(This postion shall not be used)			
088	58	(This postion shall not be used)			
089	59	(This postion shall not be used)			
090	5A	(This postion shall not be used)			